Frederick University - email settings for Outlook

Adding a new account:

1. Select the **File** menu and choose **Info**



- 2. Click the **Add Account** button.
- 3. Choose Manual setup or additional server types



5. Choose POP or IMAP



6. Click Next.

Frederick University - email settings for Outlook

Account Settings:

User Information		Test Account Settings
Your Name:	George Loizos	We recommend that you test your account to ensure that
Email Address:	ad.lg@frederick.ac.cy	
Server Information		Test Assount Settings
Account Type:	POP3	rescaccount settings
Incoming mail server:	pop3.frederick.ac.cy	Automatically test account settings when Next is clicked
Outgoing mail server (SMTP):	smtp.frederick.ac.cy	Deliver new messages to:
Logon Information		New Outlook Data File
User Name:	ad.lg	Existing Outlook Data File
Password:	****	Browse
📝 Re	emember password	
📃 Require logon using Secur	re Password Authentication	
(SPA)		More Settings

Fill in the fields as follows:

Your Name as you want it to appear on your outbound email messages

Email Address:	Your email address
Account Type:	POP3
Incoming Mail Server:	pop3.frederick.ac.cy
Outgoing Mail Server:	smtp.frederick.ac.cy
User Name:	ad.lg or cs50287@stud (for students)
Password:	your email password

Frederick University - email settings for Outlook

More Settings

1. Click the More Settings button.

Seneral Outgoing Server Advanced	General Outgoing Server Advanced
ieneral Outgoing Server Advanced My outgoing server (SMTP) requires authentication • • Use same settings as my incoming mail server • • Log on using • User Name: • Password: • • Require Secure Password • • Log on to incoming mail server before sending mail	General Outgoing Server Advanced Server Port Numbers Incoming server (POP3): 110 Use Defaults This server requires an encrypted connection (SSL) Outgoing server (SMTP): 587 Use the following type of encrypted connection: TLS Server Timeouts Short Short Long Image: Delivery Leave a copy of messages on the server Remove from server after 14 Remove from server when deleted from 'Deleted Items'
OK Cancel	OK Cancel

- 2. Click the Outgoing Server tab.
- 3. Click the "My outgoing server (SMTP) requires authentication" checkbox.
- 4. Click the Advanced tab.
 - Change the settings as shown in the above picture
- 5. Click the **OK** button.

Completing the Setup

- 1. Click **Next** on the E-mail Accounts window.
- 2. Click the **Finish** button.

Outlook is now configured to send and receive emails.